

Chief Inspector Check List for Opening the Polls

Before Election Day_

- □ Check contents of the City Clerk tote. If anything is missing, contact Clerk's Office.
- Contact the polling place to confirm voting location and where to enter on election morning. Familiarize yourself with the location. Review parking and building accessibility. Identify an Election Day facility contact person. The facility is offering the use of this location as a polling place for free! Please maintain a polite and respectful relationship with facility staff.
- Choose one poll worker scheduled to work until close to be the End of Line Officer. Record their name on the incident log.
- □ Contact each poll worker scheduled to work at your polling place so they know what to expect. Let them know where to park, which entrance to use, and whether to pack a lunch. Confirm the workers' assigned hours/shift.
- □ Review the task sheets in this binder. Decide which tasks you will assign to each poll worker at the start of the day.
- □ If there are a lot of absentee voters in your ward(s), you may complete the highlighting task on the Poll Book Table task sheet prior to Election Day. Add this time to your timesheet on Election Day.

Supply Tackle Box

Тор пау					
Binder Clips	Adapter			Rubber Fingertips	
Hablo Español Badge	Paper Clips	Rubber Bands	A A	SortKwik	Keys
Magnifying Sheet Calculator Index Tabs Signature Guides					
Sharpie Dry Erase Marker Orange & Pink Highlighters					

Bottom Bin

Letter Openers

Post-Its
Stapler
Staple Remover
Chargeable Flashlight
Scissors

Stopwatch

Tape Measure
Blue Painter's Tape

Ballot Marking Pens

Loose in Supply Tote

- □ Stickers in plastic tub
- First aid kit (if returned last election)
- □ Voter slip pads & school district highlighters
- □ Dane County security bag with seals
- □ Chief Inspector binder (yellow)
- □ Absentee binder (black)
- □ City return envelope (white)

- □ County return envelope (white)
- □ Rejected absentee envelope (manila)
- □ Duplicated ballot envelope (manila)
- □ Discarded ballot envelope (manila)
- □ Ballot security bags (3)
- □ iPad and charger

Greeter Table Folder	
 Quick Guide for greeter Ward-specific street directory Map of each ward at polling place List of polling places 	 Citywide street directory Determining Where a Person Votes Scratch paper Reference guide
Poll Book Table Folder	
 Scratch paper Quick Guides for poll book table, checking ID Poll list corrections sheet Voters without ID tally sheet 	 Acceptable photo ID picture guide Observer Guides Reverse directory 2 poll books for every ward
Registration Table Folder	
***English registration forms are in a clear container in	
 Scratch paper Proof of address cards What – Who – Four – Two reminder Quick Guide for registration Acceptable proof of residence picture guide Quick Guide for second official Quick Guide for checking ID Voters lacking proof of address tally sheet Acceptable photo IDs picture guide 	 Determining Where a Person Votes Registration transparency sheets Ward-specific street directory (3) Folder with ineligible list & handouts Folder of Spanish & Hmong reg. forms Folder for those unable to register Observer Guides Carbonless new registration poll list form Yellow accordion for completed registrations
Signage Folder	
 Legal notices for this election Reminder to post sample ballots Accessible entrance sign No firearms or weapons Voting sign with hours 	 ID petition process sign Ballots counted here sign (purple) Voting arrow signs (orange) Keep ballots dry Sign (post only if needed)
○ Ballot Table Folder	
 Second ballot log (green) Voter number reconciliation sheets Pen or touchscreen sign (light blue) 	 How to mark ballot signs Good ballot/bad ballot stickers Observer Guides
Provisional Table Folder	
 Provisional Quick Guide Quick Guide for returning provisional voter Provisional envelopes (blue) Provisional log (lilac) 	 Provisional stamp ID petition process handouts Provisional handouts (blue) Large inspectors' certificate of PV ballots
 Chief Inspector Binder Inspectors' Statement 	Observer badges
 Deserver log Election official statistics form Comments & feedback form Opening the polls task sheets Closing the polls task sheets 	 Observer badges Observer brochures Order to leave the polls form Challenge forms Challenge brochures Election Official badges
Absentee Binder	
 Absentee Inspectors' Statement Absentee log Quick Guides for processing absentees Absentee processing PowerPoint 	 Observer Guides Ineligible list Absentee bundle tracking sheet Absentee bundle tablet

Election Morning Set-Up_

- □ Meet your team onsite at 6 a.m. All poll workers should help set up the polling place.
- □ Locate and unlock the red elections security cart, using the silver key with text on both sides of the key. All contents should be removed from the cart.
- □ If possible, a poll worker who is working the entire day should take a picture of how the security cart is packed, to reference when packing supplies as the polls close.
- □ Assign someone to hand out name tags. Encourage poll workers to list pronouns on nametags if they're comfortable doing so.
- □ Assign each opening task sheet to one or two poll workers.

Opening Task	Assigned to
A – iPad	
B – Tabulator Cart	
C – Voting Booth Set Up	
D – Ballot Table	
E – Poll Book Table	
F – Registration Table	
G – Greeter Station	
H – Provisional Ballot Station	
I-Signs and Sample Ballots	
J – ExpressVote	
K – Prepare Tabulator for Counting	
L – Election Day Accessibility Checklist	

Team Meeting Before Opening Polls

Review the following with all poll workers:

- Our goal is that each eligible voter will be able to cast a ballot and have that ballot counted.
- □ Ballot styles (see chart on back page of the Inspectors' Statement).
- □ Be aware of the special needs of voters with disabilities. Provide reasonable accommodations when requested.
- $\hfill\square$ How to know when someone needs to vote curbside.
- □ Curbside voting process.
- □ Where to find these items:
 - a. Pen/paper to communicate with voters with hearing impairment.
 - b. Magnifying sheet for voters with sight impairment (top tray of supply box).
 - c. Signature guide for voters with sight impairment (top tray of supply box).
 - d. Seating for voters who have trouble standing or walking to wait to vote and maintain their place in line.
 - e. How to use the ExpressVote and how to explain the ExpressVote to voters.
- □ Give each poll worker their initial assignment. Rotate task assignments throughout the day so nobody burns out on a single task. This also protects against fraud.
- □ Tell poll workers to review the Quick Guide at each station as they begin each task. Quick Guides are found in the accordion folder for that station. The absentee quick guide is in the black binder.
- Review recent changes to election law and procedures with all poll workers. These would have been covered in training.
- Review emergency procedures including medical emergency, shelter in place and evacuation. Make sure everyone knows where to meet up if evacuation is necessary.
- Determine which clock or watch will be used for the official time. Document this on the incident log.
- □ Take a deep breath with your team of election officials.

Open the Polls Promptly at 7 a.m._

□ Make the following proclamation:

"Hear ye! Hear ye! The polls of the election are now open and will continue to be open until 8 o'clock this evening!"

Opening Task A iPad $\star \star \star$	****
 Remove the iPad from the Clerk supply tote. Turn on the power by pressing the button above the screen. Swipe up from the bottom of the screen. Enter the passcode. Press on the Teams app from the homepage. Enter the e-mail address the Clerk's Office uses to communicate with you. Press Go. Enter your Teams password. Teams will provide a number on the screen that you will need to enter on your phone for two-factor authentication. 	
 Within the Teams app, choose Teams. Select "General" under the current election. ✓ Use the Posts tab (at the top) for general communications and photos. This is where you can connect with other polling places. Keep in mind that these posts are an open record that will be saved for seven years. ✓ Use the Files tab to see how your voter turnout numbers compare to other polling places. ✓ Use the Apps tab to go to the Support Center. This is where you'll enter issues requiring support. Clerk's Office personnel and Roving Chief Inspectors are working from this tab. ✓ Use the Apps tab to jump to the Clerk's Office Resources website. ✓ Use the Apps tab to jump to the My Vote WI website. 	Verter Verter Verter Verter <td< td=""></td<>

Support Center

To notify the Clerk's Office of an issue or a question, click the <u>+New</u> box in the upper left corner.

- 1. Give your Issue a short title. For example, "Ballots needed."
- 2. Type a description in the Issue description box. For example, "We're down to 50 Header Code 23 ballots."
- 3. Choose a priority level.
- 4. Type in your ward number.
- 5. Press the Save box on the screen.

	× Car
Issue	
Enter value here	Enter value here
Short title of issue	and the second
	Describe the issue
	₹ Ward
Add the priority of this issue	Select an option



Assigned to:



All voting booths must be set up. The Clerk's Office delivered the number of booths you need to set up. State law requires one voting booth for every 200 voters your polling place had for the last November election.

Keep booths separate from other activities such as checking in and registering.

- Unlatch and open the voting booth case.
- Remove all 8 legs from inside the voting booth. The legs are folded in half with a cord inside that connects the two tubes into one.
- Insert the legs into the sockets located on the outside of the voting booth case. It is easier if two officials work together.
- Place booth in its place and adjust its stance. Unfold and place privacy screens into slots.

Possible configurations:



Accessible Voting Booth

The accessible booth must be setup with a clear path. It needs a five-foot turning radius for mobility devices. Make sure the front legs are wider than the booth itself.



Put these items on ballot table. Most items can be found in the tabulator cart.

□ Ballot marking pens (supply kit) – put in voting booths.

□ How to Mark Your Ballot signs (accordion folder).

□ Secrecy sleeves (tabulator cart).

□ Discarded ballot envelope (clerk tote).

□ Second ballot log (green, accordion folder)

□ Plastic container for voter slips (tabulator cart).

□ Ballots (tabulator cart)

□ ExpressVote ballot cards (tabulator cart emergency bin)

□ Count 50 ballots from the bottom of pile for each ballot style. Use a post-it note to remind the official who reaches that ballot to call the Clerk's Office for more ballots.

□ The last page of the Inspectors' Statement lists how many ballots you have for each style. Check that you have received the correct ballots. It is not necessary to count the ballots.

□ Fan the ballots as they come out of the package. This reduces the likelihood they will stick together.

□ Do not pre-initial any ballots. Initials are applied to each ballot only after receiving the voter slip from the voter.



Set up the registration table where it is visible to those who need to register.

Most materials for this table are in the large brown accordion folder with a black dot. Put these items on the registration table:

- □ Voter registration forms (tabulator cart)
- □ Voter registration forms in Spanish and Hmong (accordion folder)
- □ Clipboards (tabulator cart)
- □ Pens (supply kit)
- □ Proof of address abbreviation cards (accordion folder)
- Ineligible voter list if felons are known to live in ward (file folder in accordion folder)
- □ Ward-specific street directory (laminated, in accordion folder)
- Tally sheet for voters lacking proof of address (salmon, accordion folder)

Put these items at the new registration poll list (often at poll book table):

- □ Voter registration transparency sheet (accordion folder)
- □ Quick Guide for checking ID (accordion folder)
- □ Poll list for new registration/change of address (accordion folder)
- □ Yellow accordion folder for completed registrations (accordion folder)
- Designate an area for observers. It should be three to eight feet away from the registration table. Mark its boundaries with painter's tape.

* Review the Quick Guide (found in accordion folder) before working at this station.





```
Assigned to:
```


Put these items at the provisional ballot station. You will find everything but the pens in the blue accordion folder.

- □ Provisional ballot certificate envelopes (small blue envelopes)
- □ Provisional ballot "PV #" stamp
- □ Provisional voting information sheet for electors (blue handouts)
- □ ID petition process handouts
- □ Provisional ballot reporting form (lilac sheet)
- □ Inspectors' certificate for provisional ballots (big blue envelope)
- □ Pens

* Review the Quick Guide (found in accordion folder) before issuing provisional ballots.



Election Official Opening Task *I* Signs and Sample Ballots * * * * * * * * * * * * * * * * *



The signage kiosk is found in a flat blue carrying case in your security cart. Use the QR code above to watch a video tutorial on how to set up the signage kiosk.

Do not pry open.

Simply unfold the kiosk and shake it gently. Voters should be able to read the notices on both sides:

- ✓ Are you qualified to vote?
- ✓ Instructions for mail-in registrants and first-time voters
- ✓ General information on voting rights under federal laws
- ✓ Notice of election fraud
- ✓ Contact information reporting fraud or corruption

Entrance

- No firearms or weapons -- post on every external entrance to the polling place. Does not need to be posted if doors already have a sign prohibiting firearms. (red accordion folder)
- □ Accessible entrance– post on the entrance accessible to voters with disabilities. This might also be at the main entrance. (red accordion folder)
- □ Polling hours post at main entrance (red accordion folder)

- □ Directional signs with arrows to direct voters through the building to where voting takes place (bright orange, red accordion folder)
- □ At least 2 sample ballots for each ballot style (yellow, tabulator cart) post for voters to see as they enter the voting room
- □ ID petition process sign (accordion folder) post for voters to see as they enter the voting room
- □ Legal notices (accordion folder) post for voters to see as they enter voting room

Registration Table

□ Register tabletop sign (yellow, security cart) – post at registration table

Poll Book Table

- □ Voter check-in tabletop sign (green, security cart) post at poll book table
- □ Ballot tabletop sign (blue, security cart) post at ballot table

Tabulator

□ Ballot counted here (purple, accordion folder) – post on tabulator

Outside

- □ Flag standard (security cart) set at polling entrance before polls open
- □ Curbside voting sign (blue box, in security cart) fill base of the sign with water so it does not blow over
- □ Feather flag next to curbside voting sign (long canvas tote inside security cart). Use QR code for a video tutorial.



□ Vote yard signs with arrows to help point voters to the polling place (security cart). Consider first-time voters traveling from all directions. Make sure signage helps direct them to the polling place.

Post everything in the red Signage folder except the Keep Ballot Dry sign (unless it is raining).

□ The person taking down signs tonight will need to know where to look. Locate Closing Task Sheet A in the Chief Inspector's yellow binder. Leave a note about where to locate signage.



Federal law requires that the ExpressVote be set up at every polling place. Set it up so people standing in line cannot see how someone is voting. Provide a turning radius of 5 feet by 5 feet for voters in mobility devices.

Place ExpressVote on a table or voting booth at least 30 inches wide. Make sure table is 28 to 34 inches high with a knee clearance of 19 inches. You have a measuring tape in the supply kit.



1. Determine best location

Use the guidelines above to find a spot convenient for voters using a mobility device. Place a chair nearby for voters without mobility devices who will use the ExpressVote.

2. Remove from Case

Remove the ExpressVote from its carrying case. Remove the power cord and headphones from the pocket on the outside of the case. Plug the small circular end of the power cord into the port on the back of the ExpressVote (flat side up). Plug the power cord into the wall. Tilt the machine back onto its metal support legs.



3. Power Up

Use the barrel key to unlock the security access door on the left side of the machine. Set the power switch to On. Verify that the mode switch is set to Voter. The screen will say that the machine is starting up.



(continued on next page)

ExpressVote (continued)

4. Enter Election Code

Use the touch screen to enter the case sensitive Election Code. You will need to touch the shift key on the touch screen before typing this code. After entering this code, press Accept on the screen.

Once the "To begin Voting, insert your card" screen appears, close and lock the access door.

5. Position Privacy Screen

Locate the cardboard Vote privacy screen from the tabulator cart. Position it around the ExpressVote.

6. Test

Before the polls open, test the ExpressVote to make sure it is working. Write "test" at the bottom of an ExpressVote ballot card.

Insert the ballot card into the ExpressVote feed tray. The cut corner should be facing right and at the top of the blank card. If your polling place has more than one ballot style, select the ward and ballot style on the touchscreen. Polling places with only one ballot style will see the Ready for Voting screen right away.

Use the touch screen to select any candidates. You are verifying that calibration was not affected during delivery. Make sure the ExpressVote marks the ballot card for the candidates selected. If the ExpressVote does not accurately mark the ballot card, go through the calibration process on the next page. **Make sure the ExpressVote is set up for the ward(s) at your polling place.**

Upon completion, reinsert the ballot card in the **ExpressVote**. The ExpressVote will read the barcode and tell you which candidates were selected. After ejecting, partially tear and discard the test ballot card in the Discarded Ballot envelope. The Election Day test ballot card is never fed into the tabulator.

Election Officials Voting on ExpressVote

Poll workers who vote at this polling location are encouraged to use the ExpressVote. Any voter is welcome to use the ExpressVote. Do not hover over voters using the ExpressVote. Do not watch voters make their selections.

ExpressVote Troubleshooting

Calibration

At times, the ExpressVote will need to be recalibrated. This is because it travels across bumpy roads when delivered to the polling place. If the ExpressVote is not marking the ballot for the candidates selected, complete these steps.

- a. Open the security panel on the left side of the machine.
- a. Change the Mode switch to Official.
- b. From the Main Menu, choose Calibrate Touch Screen.
- c. Choose Calibrate to confirm the action.
- d. Align the touch points by pressing and releasing the center of each crosshair that appears on the screen.
- e. If satisfied with the calibration, press anywhere on the screen to continue.
- f. Change the mode switch back to Voter.
- g. Close and lock the security panel.

Card Jam

After the ExpressVote prints a ballot card, the card may get stuck in the machine.

a. Open the security compartment on the left side of the machine. Change the Mode Switch to Official. When the Main Menu appears, press Eject Card. When card ejects, change Mode Switch back to Voter.

If the card does not eject:

- a. Open the security panel on the right side of the machine.
- b. Locate the card and **gently** pull the card out of the machine. If the card is not removed gently, it can tear. In that case, the voter will need to spoil the card and be issued another card.
- c. Remove the card jam, being careful not to rip the paper.
- d. Close and relock the security panel.

Card left in ExpressVote

This error message appears after the ExpressVote has been idle, with a card inserted for 5 minutes: "!Alert The ExpressVote requires attention. Ask an Election Official for help. Election Official: A previous voting session has expired and the card is being held within the Voter Assist Terminal. Switch to Official Mode to Resolve Error."

a. Open the left security compartment and switch the Mode to Official. The card can then be ejected. After ejecting card, switch Mode back to Voter.

Assigned to:



(continued on next page)

Prepare Tabulator for Counting (continued)

6. The DS200 will need you to enter the Election Security Code. The Election Security Code is case sensitive. Enter the Election Security Code on the touch screen and then press Accept. You will need to press the shift key on the touch screen before typing the first letter. After entering this code, press Accept.

The DS200 will print the Configuration Report. **Do not tear off tape until polls are closed and you have run a results tape.**

7. Verify that the time (upper right corner of screen) is correct. If the time is incorrect, this is your only opportunity to adjust the time. Follow the steps for changing the time in the tabulator troubleshooting instructions <u>before</u> you select Open Poll. The tabulator troubleshooting instructions can be found on the next few pages.



- 8. Press "Open Poll" on the touch screen. The DS200 will automatically print a zero tape. See troubleshooting on next page if zero tape does not print.
- □ 9. Press "Go to Voting Mode" on the touch screen.
- 10. Verify all contests, candidates and referenda appear on the zero tape with zero votes cast. Verify that your polling place wards appear on your zero tape.

(continued on next page)

Prepare Tabulator for Counting (continued) □ 11. Verify the public count (on touch screen) reads 0. Touch screen should say, "Welcome. Please insert your ballot." \rightarrow If public count does not read 0, document this on the incident log and immediately call the Clerk's Office. You will need to zero out the machine; see DS200 Troubleshooting on the following pages. Ignore the "protected count" on the screen. The protected count is like an odometer. It shows the total number of ballots ever fed into this DS200 machine. □ 12. Verify the DS200 serial number (printed on zero tape). Initial the red line on the front page of the Inspectors' Statement that says you have verified the tabulator serial number. □ 13. In the margin by the signature lines on the zero tape, write the serial number of the blue tamper-evident sticker seal found on top of the scanner. □ 14. Three officials should sign the zero tape before the polls open. If left-handed, it may be easiest to sign your name upside-down. □ 15. Do not tear off tape until polls are closed and you have run the results. To discourage people from tearing off the zero tape, fold the zero/results tape and put a paperclip or binder clip on it. □ 16. Verify that the tabulator is running on power from the outlet it is plugged into, and not running on battery power. Look for the plug icon in the upper right corner of the touch screen. An icon showing space between the plugs indicate that tabulator is not plugged in. 17. Record successful tabulator setup on the incident log. 04/04/2017 🕒 📙 💉 10:55 AM E M # 10:55 AM ↑ Plugged in The poll is open and the voting device is now ready for voting. For report options press "Report Options" now. To start accepting ballots press "Go to Voting Mode" Please close the access door and place the key a secure location.

DS200 Troubleshooting

DS200 does not start up

You may have opened the screen before plugging in the machine.

- a. Close the screen.
- b. Plug in the tabulator
- c. Open the screen.

Print doesn't show up on tape

The Clerks' Office may have inserted the tape in the wrong direction.

- a. Remove sticker seal from top of access door. Document this on the Incident Log. Affix the sticker seal to the front of the white Dane County Clerk envelope.
- b. Unlock the access door, located above the printer. This will allow you to access the printer release lever.
- c. Press the lever to unlock and open the printer door.
- d. Make sure the glossy side of the thermal paper is facing the thermal printer. The glossy side will leave a gray mark when scratched.



Reprinting Zero Tape

- **a.** Press Tools in the upper right corner of the screen.
- **b.** Enter Election Code.
- c. Select Report Options.
- d. On the next screen, select
 - ✓ Zero Totals
 - ✓ Detailed report format
 - ✓ Precinct report level
 - ✓ Include Affidavit
- e. Document this on the incident log.



DS200 Troubleshooting, continued

Unplugged power icon

The unplugged icon in the upper right corner of the screen indicates that the tabulator is not getting power from the wall outlet. Try another outlet. Make sure the power cord is completely plugged into the power port in the back of the tabulator.



218 Pf

Time is wrong

a. Press the Admin button on the upper right corner of the screen.

Public Count: 0

- b. Press "Log In" and enter the Administration Code. You will need to press the shift key on the touch screen before typing the code. Press accept.
- c. From the Admin menu on the left, press "System Settings."
- d. Press **Date and Time Options** under System Settings.
- e. Press **Change Time** to proceed with updating the time.
- f. Select the field to update (hour, minute, or AM/PM) by pressing on the corresponding box.
- g. Correct time by using the arrows to make adjustments.
- h. Press Apply to save the changes.
- i. Press **Back** to return to previous screen.
- j. On the next screen, press Apply again.
- k. Press OK.
- I. Press Logout and, finally, Exit (bottom left).
- m. Press Open Poll.



DS200 Troubleshooting, continued

Public Count Does Not Read 0000 for Opening the Polls

If public count does not read 0000, document on incident log and do this:

- □ Call the Clerk's Office to notify them of the situation.
- □ If the blue sticker seal says "void open," the Clerk's Office will set up and test a new tabulator at your polling place.
- □ If the blue sticker seal does not say "void open," tear the blue sticker seal off the top of the scanner. Affix the blue sticker seal to the City Clerk envelope.
- Use the barrel key to unlock the small access door from which you have just removed the sticker seal on top of the scanner. Pressing the key into the keyhole, turn the key to the left (counter-clockwise) a quarter of a turn. Lift the panel up.
- Press the Close Polls button for approximately 5 seconds. The touch screen will ask whether you want to close the polls. From this menu, choose Reopen Polls.
- □ Using the keypad, enter the override code.
- □ From the Reopen Polls menu, chose Clear Counts & Continue.

Ballots counted but not released to the bin (after polls have opened)

Check the back of the tabulator to make sure the silver bar is down (below the battery) and latched into the white clasp. If the silver bar is up in the unlocked position (in front of the battery), ballots will jam.



DS200 Troubleshooting, continued





Tabulator screen is frozen

Tear the blue sticker seal off the top of the scanner. Affix sticker seal to County Clerk envelope. Use the barrel key to unlock the compartment from which you just removed the seal. Lift access door open. Press and hold the power button for as long as it would take for the UW band to play "Varsity."

Watch the screen. The screen will go blank as the tabulator begins a hard reboot. Once you get a white screen with five lines of text, **immediately press the close poll button**. The final sentence on the white screen is asking you to press the close poll button to calibrate the screen.



You will next be prompted to touch a circle on the upper left corner of the screen. The touch screen needs one pound of pressure from your finger. When you touch the circle it will turn black.

Next, you will be prompted to touch a circle on the lower right corner of the screen. When you touch the circle it will turn black. The touch screen is now recalibrated.

Press the green bar asking you to save and exit. The tabulator should be back in operation.

Document the recalibration on your incident log.

Opening Task *L* Election Day Accessibility Checklist *****

Assess whether the polling place has barriers for people with disabilities. If you identify any barriers, inform the Clerk's Office as soon as possible.

Parking

Accessible parking must be kept clear of snow, piles of leaves, or other obstacles to persons with disabilities in order to be accessible.

For polling locations that have parking lots:

- □ Accessible space(s) are clearly marked with the standard accessible parking sign.
- \Box The accessible space(s) are located nearest to the accessible entrance.
- $\hfill\square$ There is at least one van-accessible space.
- \Box There is an accessible way to get from the parking lot to the sidewalk.
- \Box The parking lot is paved.

For polling locations that do not have parking lots:

□ There is an accessible passenger drop-off area, or temporary on or off street accessible parking that could be designated on Election Day.

Pathways to the Building

- □ The path to the accessible entrance is clearly marked with large print signs if it is different from the primary route to the building.
- □ The path of travel is free of breaks and edges and is clear of debris such as snow, ice and leaves, and low-hanging objects such as tree branches.
- □ The path of travel has the necessary curb cuts and ramps so that a person using a mobility device could access the building with ease.
- \Box All ramps have handrails (and edge protection), if necessary.
- \Box The path of travel is well-lit.

Entrance to the Building

- \Box The entrance to the building is free of steps or has a ramp or elevator.
- \Box The accessible entrance to the building is unlocked.
- □ Accessible entrance has an automatic door opener or a call button, or there is someone stationed at the door to open it.
- □ There is signage or a greeter stationed at the entrance with information on requesting curbside voting.

Travel within Building

- □ Accessible route to the voting area is clearly marked with large print signs if it is different from the main route and/or if not immediately inside accessible entrance.
- □ Interior doors along accessible route are unlocked and either have automatic doors or are propped open.
- \Box If there are stairs to the voting area, an accessible elevator is available.
- □ Hallways are well-lit and free of low-hanging objects and items protruding from the wall or sitting on the floor.
- □ All rugs and mats along the accessible route have low pile and are securely fastened (or removed).

Voting Area

- □ Instructions for voting are printed in Large Print (18 point font or larger) and displayed in a convenient and obvious location.
- □ The path of travel in the voting area is wide enough for an individual using a mobility device to navigate and turn around with ease (minimum of 5x5 feet).
- Poll workers have set up the accessible voting booth that is extra wide at the bottom (at least 36 inches), and at good height (between 28 and 34 inches) to allow someone who uses a mobility device to use it comfortably.
- Poll workers have set up the ExpressVote on a table or voting booth that is extra wide at the bottom (at least 36 inches), and at good height (between 28 and 34 inches) to allow someone who uses a mobility device to use it comfortably and reach all parts of the voting equipment.
- $\hfill\square$ The ExpressVote is set up in such a way that it is
 - $\hfill\square$ Housed in the same area of the room as all the other voting booths
 - □ Strategically placed to ensure the privacy of the voter using the machine **and** contain a privacy screen.

Election Day Accessibility Checklist (page 3 of 4)

- □ The ExpressVote is turned on, tested, and in proper working order for electors to use when the polls open on Election Day. The test ballot has been partially torn and placed in the Discarded Ballot envelope.
 - □ All accessible features of the ExpressVote are set up and working, including tactile devices and headphones
- □ The polling location has the following:
 - Signature guide to assist someone to sign their name in a straight line (found in top tray of supply kit)
 - Pen and paper to communicate with someone who is deaf or hard of hearing (found in bottom of supply kit).
 - Magnifying glass to be used by someone with a sight impairment (found in top tray of supply kit, probably in a plastic sleeve).
 - Extra seating and a policy to allow voters who have trouble standing or walking to wait to vote and maintain their place in line.
 - ✓ Lighting at every space in the voting area.

Interactions with Voters

- □ Poll workers are aware of the special needs of voters with disabilities and are willing to provide reasonable accommodations when requested.
- □ Poll workers are aware of the assistant process:
 - □ Any elector may have an assistant. The assistant can be anyone, except the elector's union representative or employer, and the assistant does not have to be a qualified elector.
 - □ Electors may have an assistant **state their name and address** for them if they are unable.

An elector can direct an assistant to mark their ballot and insert the ballot into the ballot box or tabulator. The assistant must sign the ballot in the designated location. Poll workers will note on the poll book next to the voter's name, "Assisted by," followed by the name and address of the person providing assistance in marking the ballot.

□ If an elector is unable to sign the poll book due to a disability, poll workers will write "Exempt by order of inspectors" in the voter signature box.

Poll workers have reviewed the Poll Worker Common Courtesy Checklist (see following page).

There is a feasible plan in place to identify when a voter wants to vote curbside,
such as having signage, a phone number, or a greeter stationed outside, and poll
workers are aware of the curbside voting policy.

Troubleshooting for Van Accessible Parking Spots

Some of our polling place audits have identified issues with van accessible parking spots. If your polling location has the supplies noted below, it means that you have a van accessible parking issue to resolve on election morning.

□ Four red cones and a roll of yellow caution tape

Use these materials to make the van accessible parking space wider.

- Position the cones to incorporate two parking spaces the signed accessible space and the one next to it (approximately 96" width) – so a van could park and unload there.
- 2. Using duct tape, affix the caution tape at the top of the cones around three sides of the widened parking spot.
- $\hfill\square$ Van accessible parking space sign

The sign for a van accessible parking space should be 60 inches high. If the Clerk's Office has provided you with a portable van accessible parking sign, place the sign at the van accessible parking space for your polling location.

Your clerk will have more detailed information about accessibility rules and laws.

Wisconsin Elections Commission

Elections.wi.gov/assisting-voters-disabilities

Disability Vote Coalition

Disabilityvote.org

U.S. Department of Justice ADA Checklist for Polling Places

www.ada.gov/votingck.htm

This checklist was created by Disability Rights Wisconsin (DRW) and reproduced by the Wisconsin Elections Commission and Accessibility Advisory Committee with permission of DRW. If you have questions about this checklist or about accessibility, contact the Wisconsin Elections Commission at 608/261-2028 or the DRW Voter Hotline at 844/DIS-VOTE (844/347-8683).

Common Sense and Common Courtesy

Many election inspectors have had little interaction with people with disabilities. Here are a few courtesies and guidelines.

- ★ State and federal law permits voters with disabilities to be accompanied and to receive assistance by another person in the voting booth.
- ★ Remember that all voters deserve courteous attention in exercising their right as citizens to vote.
- ★ Be considerate of the extra time it might take for a person with a disability or an elderly person to get things done.
- ★ Give unhurried attention to a person who has difficulty speaking.
- ★ Speak directly to the person who has a disability rather than just addressing a companion who may be accompanying them.
- ★ Speak calmly, slowly, and directly to a person who is hard of hearing. Your facial expressions, gestures, and body movements help in understanding. Don't shout or speak in the person's ear. If full understanding is doubtful, try writing a note to the person.
- ★ A notepad, found in the bottom of your supply kit, should be available to assist communication with electors who are deaf or hard-of-hearing.
- ★ Before pushing someone in a wheelchair, ask if you may do so and how you should proceed.
- ★ Greet a person who is visually impaired by letting the person know who and where you are.
- ★ Have a signature guide, found in the top tray of your supply kit, available for signing the poll book or registration form.
- ★ When offering walking assistance, allow the person to take your arm and tell them if you are approaching steps or inclines or are turning right or left.
- ★ Animals that assist people with disabilities must be admitted into all buildings. Such animals are highly trained and need no special care other than that provided by the owner.